

What is New in Release 2.1.1

Shortcut Keys

- a) In the Scan Screen the Function Keys are now sorted as they are on the keyboard.
- b) You can enter shortcuts without a Caption.
- c) The Caption on the shortcut key will be the concatenation of the different definitions in the case that you have more than one definition for the same shortcut key. This is useful in the case when you want to assign values to more than one index so you will need to define the same shortcut key several times.

Scan Screen

- a) When you are doing data entry you can now use the “TAB” key to move between fields. This is in addition to the “ENTER” key as before.
- b) When you are doing data entry the whole field will now be selected when you “TAB” or “ENTER” into it.

MICR Parser

- a) It now allows you to remove the spaces and special characters in the different fields.
- b) The MICR Parser now features a filter pattern generator that allows user defined patterns in addition to the included pre-defined patterns. This new feature provides the means to add new filters as new MICR patterns are found to enhance and perfect the parsing results.

Merge of Batches and Jobs

- a) You can now merge multiple jobs into a single job, move jobs from one batch to a different batch or merge multiple batches. These operations are only allowed between batches or jobs belonging to the same configuration.

View Layout Definition

- a) Now you can define the layout of the display of indexes on the job or batch view screen. You can also define in what order the indexes will be displayed and also indicate if you want to display the internal indexes (Item #, Job # and Batch).
- b) You can also define what view will be the “default” view. The thumbnail page will also use the selected view.
- c) The program will save the view used by each user and restore it when the user logs back in.
- d) The configuration import and export processes also save the views defined with that configuration.

New User Definition Permissions

- a) The following new permissions were added to the User definition: Delete Batches, Delete Jobs, Create or Change Views, Delete Views and Merge Batches and Jobs.

Search and Sort

- a) You can now use the internal indexes (Item #, Job # and Batch) for searching or sorting.